

primesieve

Generated by Doxygen 1.9.4

1 primesieve	1
1.1 About	1
1.2 Installation	1
1.3 C API	1
1.4 C++ API	1
1.5 Performance tips	2
2 Hierarchical Index	3
2.1 Class Hierarchy	3
3 Class Index	5
3.1 Class List	5
4 File Index	7
4.1 File List	7
5 Class Documentation	9
5.1 primesieve::iterator Struct Reference	9
5.1.1 Detailed Description	10
5.1.2 Constructor & Destructor Documentation	10
5.1.2.1 iterator() [1/2]	10
5.1.2.2 iterator() [2/2]	10
5.1.3 Member Function Documentation	11
5.1.3.1 clear()	11
5.1.3.2 jump_to()	11
5.1.3.3 next_prime()	11
5.1.3.4 prev_prime()	12
5.2 primesieve::primesieve_error Class Reference	12
5.2.1 Detailed Description	13
5.3 primesieve_iterator Struct Reference	13
5.3.1 Detailed Description	13
6 File Documentation	15
6.1 primesieve.h File Reference	15
6.1.1 Detailed Description	17
6.1.2 Enumeration Type Documentation	17
6.1.2.1 anonymous enum	17
6.1.3 Function Documentation	17
6.1.3.1 primesieve_count_primes()	17
6.1.3.2 primesieve_count_quadruplets()	18
6.1.3.3 primesieve_count_quintuplets()	18
6.1.3.4 primesieve_count_sextuplets()	18
6.1.3.5 primesieve_count_triplets()	19
6.1.3.6 primesieve_count_twins()	19

6.1.3.7 primesieve_generate_n_primes()	19
6.1.3.8 primesieve_generate_primes()	19
6.1.3.9 primesieve_get_max_stop()	20
6.1.3.10 primesieve_nth_prime()	20
6.1.3.11 primesieve_set_num_threads()	21
6.1.3.12 primesieve_set_sieve_size()	21
6.2 primesieve.hpp File Reference	21
6.2.1 Detailed Description	23
6.2.2 Function Documentation	23
6.2.2.1 count_primes()	23
6.2.2.2 count_quadruplets()	23
6.2.2.3 count_quintuplets()	24
6.2.2.4 count_sextuplets()	24
6.2.2.5 count_triplets()	24
6.2.2.6 count_twins()	24
6.2.2.7 generate_n_primes() [1/2]	24
6.2.2.8 generate_n_primes() [2/2]	25
6.2.2.9 generate_primes() [1/2]	25
6.2.2.10 generate_primes() [2/2]	25
6.2.2.11 get_max_stop()	25
6.2.2.12 nth_prime()	26
6.2.2.13 set_num_threads()	26
6.2.2.14 set_sieve_size()	26
6.3 iterator.h File Reference	27
6.3.1 Detailed Description	28
6.3.2 Function Documentation	28
6.3.2.1 primesieve_clear()	28
6.3.2.2 primesieve_jump_to()	28
6.3.2.3 primesieve_next_prime()	29
6.3.2.4 primesieve_prev_prime()	29
6.3.2.5 primesieve_skipto()	29
6.4 iterator.hpp File Reference	30
6.4.1 Detailed Description	31
6.5 primesieve_error.hpp File Reference	31
6.5.1 Detailed Description	32
7 Example Documentation	33
7.1 count_primes.cpp	33
7.2 primesieve_iterator.cpp	33
7.3 nth_prime.cpp	34
7.4 prev_prime.cpp	34
7.5 primes_vector.cpp	34

7.6 count_primes.c	35
7.7 prev_prime.c	35
7.8 primesieve_iterator.c	35
7.9 nth_prime.c	36
7.10 primes_array.c	36
Index	37

Chapter 1

primesieve

1.1 About

primesieve is a C/C++ library for quickly generating prime numbers. It generates the primes below 10^9 in just 0.2 seconds on a single core of an Intel Core i7-6700 3.4GHz CPU from 2015. primesieve can generate primes and prime k-tuplets up to 2^{64} . primesieve's memory requirement is about $\pi(\sqrt{n}) * 8$ bytes per thread, its run-time complexity is $O(n \log \log n)$ operations. The recommended way to get started is to first have a look at a few C or C++ example programs. The most common use cases are iterating over primes using `next_prime()` or `prev_prime()` and storing primes in a vector or an array.

For more information please visit <https://github.com/kimwalisch/primesieve>.

1.2 Installation

- [Install libprimesieve using package manager.](#)
- [Build libprimesieve from source.](#)

1.3 C API

- [primesieve.h](#) - primesieve C header.
- [primesieve_iterator](#) - Provides the `primesieve_next_prime()` and `primesieve_prev_prime()` functions.
- [C examples](#) - Example programs that show how to use libprimesieve.
- [C error handling](#) - How to detect and handle errors.
- [Link against libprimesieve](#).

1.4 C++ API

- [primesieve.hpp](#) - primesieve C++ header.
- [primesieve::iterator](#) - Provides the `next_prime()` and `prev_prime()` methods.
- [C++ examples](#) - Example programs that show how to use libprimesieve.
- [C++ error handling](#) - How to detect and handle errors.
- [Link against libprimesieve](#).

1.5 Performance tips

- `libprimesieve performance tips`.
- `libprimesieve multi-threading tips`.

Chapter 2

Hierarchical Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

primesieve::iterator	9
primesieve_iterator	13
std::runtime_error		
primesieve::primesieve_error	12

Chapter 3

Class Index

3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

primesieve::iterator	Primesieve::iterator allows to easily iterate over primes both forwards and backwards	9
primesieve::primesieve_error	Primesieve throws a primesieve_error exception if an error occurs e.g	12
primesieve_iterator	C prime iterator, please refer to iterator.h for more information	13

Chapter 4

File Index

4.1 File List

Here is a list of all documented files with brief descriptions:

primesieve.h	
Primesieve C API	15
primesieve.hpp	
Primesieve C++ API	21
iterator.h	
Primesieve_iterator allows to easily iterate over primes both forwards and backwards	27
iterator.hpp	
Primesieve::iterator allows to easily iterate (forwards and backwards) over prime numbers	30
primesieve_error.hpp	
The primesieve_error class is used for all exceptions within primesieve	31

Chapter 5

Class Documentation

5.1 primesieve::iterator Struct Reference

`primesieve::iterator` allows to easily iterate over primes both forwards and backwards.

```
#include <iterator.hpp>
```

Public Member Functions

- `iterator () noexcept`
Create a new iterator object.
- `iterator (uint64_t start, uint64_t stop_hint=std::numeric_limits< uint64_t >::max()) noexcept`
Create a new iterator object.
- `void jump_to (uint64_t start, uint64_t stop_hint=std::numeric_limits< uint64_t >::max()) noexcept`
Reset the primesieve iterator to start.
- `iterator (const iterator &)=delete`
primesieve::iterator objects cannot be copied.
- `iterator & operator=(const iterator &)=delete`
- `iterator (iterator &&) noexcept`
primesieve::iterator objects support move semantics.
- `iterator & operator=(iterator &&) noexcept`
- `~iterator ()`
Frees all memory.
- `void clear () noexcept`
Reset the start number to 0 and free most memory.
- `void generate_next_primes ()`
- `void generate_prev_primes ()`
- `uint64_t next_prime ()`
Get the next prime.
- `uint64_t prev_prime ()`
Get the previous prime.

Public Attributes

- std::size_t **i_**
- std::size_t **size_**
- uint64_t **start_**
- uint64_t **stop_hint_**
- uint64_t * **primes_**
- void * **memory_**

5.1.1 Detailed Description

[primesieve::iterator](#) allows to easily iterate over primes both forwards and backwards.

Generating the first prime has a complexity of $O(r \log \log r)$ operations with $r = n^{0.5}$, after that any additional prime is generated in amortized $O(\log n \log \log n)$ operations. The memory usage is $\text{PrimePi}(n^{0.5}) * 8$ bytes.

Examples

[prev_prime.cpp](#), and [primesieve_iterator.cpp](#).

5.1.2 Constructor & Destructor Documentation

5.1.2.1 iterator() [1/2]

```
primesieve::iterator::iterator () [noexcept]
```

Create a new iterator object.

Generate primes ≥ 0 . The start number is default initialized to 0 and the stop_hint is default initialized UINT64_MAX .

5.1.2.2 iterator() [2/2]

```
primesieve::iterator::iterator (
    uint64_t start,
    uint64_t stop_hint = std::numeric_limits< uint64_t >::max() ) [noexcept]
```

Create a new iterator object.

Parameters

start	Generate primes \geq start (or \leq start).
stop_hint	Stop number optimization hint, gives significant speed up if few primes are generated. E.g. if you want to generate the primes ≤ 1000 use stop_hint = 1000.

5.1.3 Member Function Documentation

5.1.3.1 clear()

```
void primesieve::iterator::clear ( ) [noexcept]
```

Reset the start number to 0 and free most memory.

Keeps some smaller data structures in memory (e.g. the PreSieve object) that are useful if the `primesieve::iterator` is reused. The remaining memory uses at most 200 kilobytes.

5.1.3.2 jump_to()

```
void primesieve::iterator::jump_to (
    uint64_t start,
    uint64_t stop_hint = std::numeric_limits< uint64_t >::max() ) [noexcept]
```

Reset the primesieve iterator to start.

Parameters

<code>start</code>	Generate primes \geq start (or \leq start).
<code>stop_hint</code>	Stop number optimization hint, gives significant speed up if few primes are generated. E.g. if you want to generate the primes ≤ 1000 use <code>stop_hint = 1000</code> .

Examples

[prev_prime.cpp](#).

5.1.3.3 next_prime()

```
uint64_t primesieve::iterator::next_prime ( ) [inline]
```

Get the next prime.

Throws a `primesieve::primesieve_error` exception (derived from `std::runtime_error`) if any error occurs.

Examples

[primesieve_iterator.cpp](#).

5.1.3.4 prev_prime()

```
uint64_t primesieve::iterator::prev_prime () [inline]
```

Get the previous prime.

`prev_prime(n)` returns 0 for $n \leq 2$. Note that `next_prime()` runs up to 2x faster than `prev_prime()`. Hence if the same algorithm can be written using either `prev_prime()` or `next_prime()` it is preferable to use `next_prime()`.

Examples

[prev_prime.cpp](#).

The documentation for this struct was generated from the following file:


- [iterator.hpp](#)

5.2 primesieve::primesieve_error Class Reference


primesieve throws a `primesieve_error` exception if an error occurs e.g.

```
#include <primesieve_error.hpp>
```

Inheritance diagram for `primesieve::primesieve_error`:



Collaboration diagram for `primesieve::primesieve_error`:



Public Member Functions

- [primesieve_error](#) (const std::string &msg)

5.2.1 Detailed Description

primesieve throws a [primesieve_error](#) exception if an error occurs e.g.

prime > 2⁶⁴.

The documentation for this class was generated from the following file:

- [primesieve_error.hpp](#)

5.3 primesieve_iterator Struct Reference

C prime iterator, please refer to [iterator.h](#) for more information.

```
#include <iterator.h>
```

Public Attributes

- `size_t i`
- `size_t size`
- `uint64_t start`
- `uint64_t stop_hint`
- `uint64_t * primes`
- `void * memory`
- `int is_error`

5.3.1 Detailed Description

C prime iterator, please refer to [iterator.h](#) for more information.

Examples

[prev_prime.c](#), and [primesieve_iterator.c](#).

The documentation for this struct was generated from the following file:

- [iterator.h](#)


Chapter 6

File Documentation

6.1 primesieve.h File Reference

primesieve C API.

```
#include <primesieve/iterator.h>
#include <stdint.h>
#include <stddef.h>
Include dependency graph for primesieve.h:
```



Macros

- #define **PRIMESIEVE_VERSION** "11.0"
- #define **PRIMESIEVE_VERSION_MAJOR** 11
- #define **PRIMESIEVE_VERSION_MINOR** 0
- #define **PRIMESIEVE_ERROR** ((uint64_t)~((uint64_t) 0))

primesieve functions return PRIMESIEVE_ERROR (UINT64_MAX) if any error occurs.

Enumerations

- enum {
 SHORT_PRIMES , USHORT_PRIMES , INT_PRIMES , UINT_PRIMES ,
 LONG_PRIMES , ULONG_PRIMES , LONGLONG_PRIMES , ULONGLONG_PRIMES ,
 INT16_PRIMES , UINT16_PRIMES , INT32_PRIMES , UINT32_PRIMES ,
 INT64_PRIMES , UINT64_PRIMES }

Functions

- void * **primesieve_generate_primes** (uint64_t start, uint64_t stop, size_t *size, int type)

Get an array with the primes inside the interval [start, stop].
- void * **primesieve_generate_n_primes** (uint64_t n, uint64_t start, int type)

Get an array with the first n primes >= start.
- uint64_t **primesieve_nth_prime** (int64_t n, uint64_t start)

Find the nth prime.
- uint64_t **primesieve_count_primes** (uint64_t start, uint64_t stop)

Count the primes within the interval [start, stop].
- uint64_t **primesieve_count_twins** (uint64_t start, uint64_t stop)

Count the twin primes within the interval [start, stop].
- uint64_t **primesieve_count_triplets** (uint64_t start, uint64_t stop)

Count the prime triplets within the interval [start, stop].
- uint64_t **primesieve_count_quadruplets** (uint64_t start, uint64_t stop)

Count the prime quadruplets within the interval [start, stop].
- uint64_t **primesieve_count_quintuplets** (uint64_t start, uint64_t stop)

Count the prime quintuplets within the interval [start, stop].
- uint64_t **primesieve_count_sextuplets** (uint64_t start, uint64_t stop)

Count the prime sextuplets within the interval [start, stop].
- void **primesieve_print_primes** (uint64_t start, uint64_t stop)

Print the primes within the interval [start, stop] to the standard output.
- void **primesieve_print_twins** (uint64_t start, uint64_t stop)

Print the twin primes within the interval [start, stop] to the standard output.
- void **primesieve_print_triplets** (uint64_t start, uint64_t stop)

Print the prime triplets within the interval [start, stop] to the standard output.
- void **primesieve_print_quadruplets** (uint64_t start, uint64_t stop)

Print the prime quadruplets within the interval [start, stop] to the standard output.
- void **primesieve_print_quintuplets** (uint64_t start, uint64_t stop)

Print the prime quintuplets within the interval [start, stop] to the standard output.
- void **primesieve_print_sextuplets** (uint64_t start, uint64_t stop)

Print the prime sextuplets within the interval [start, stop] to the standard output.
- uint64_t **primesieve_get_max_stop** ()

Returns the largest valid stop number for primesieve.
- int **primesieve_get_sieve_size** ()

Get the current set sieve size in KiB.
- int **primesieve_get_num_threads** ()

Get the current set number of threads.
- void **primesieve_set_sieve_size** (int sieve_size)

Set the sieve size in KiB (kibibyte).
- void **primesieve_set_num_threads** (int num_threads)

*Set the number of threads for use in **primesieve_count_***() and **primesieve_nth_prime**().*
- void **primesieve_free** (void *primes)

*Deallocate a primes array created using the **primesieve_generate_primes()** or **primesieve_generate_n_primes()** functions.*
- const char * **primesieve_version** ()

Get the primesieve version number, in the form "i.j"

6.1.1 Detailed Description

primesieve C API.

primesieve is a library for quickly generating prime numbers. If an error occurs, primesieve functions with a `uint64_t` return type return `PRIMESIEVE_ERROR` and the corresponding error message is printed to the standard error stream. `libprimesieve` also sets the C `errno` variable to `EDOM` if an error occurs.

Copyright (C) 2022 Kim Walisch, kim.walisch@gmail.com

This file is distributed under the BSD License.

6.1.2 Enumeration Type Documentation

6.1.2.1 anonymous enum

```
anonymous enum
```

Enumerator

<code>SHORT_PRIMES</code>	Generate primes of short type.
<code>USHORT_PRIMES</code>	Generate primes of unsigned short type.
<code>INT_PRIMES</code>	Generate primes of int type.
<code>UINT_PRIMES</code>	Generate primes of unsigned int type.
<code>LONG_PRIMES</code>	Generate primes of long type.
<code>ULONG_PRIMES</code>	Generate primes of unsigned long type.
<code>LONGLONG_PRIMES</code>	Generate primes of long long type.
<code>ULLONGLONG_PRIMES</code>	Generate primes of unsigned long long type.
<code>INT16_PRIMES</code>	Generate primes of <code>int16_t</code> type.
<code>UINT16_PRIMES</code>	Generate primes of <code>uint16_t</code> type.
<code>INT32_PRIMES</code>	Generate primes of <code>int32_t</code> type.
<code>UINT32_PRIMES</code>	Generate primes of <code>uint32_t</code> type.
<code>INT64_PRIMES</code>	Generate primes of <code>int64_t</code> type.
<code>UINT64_PRIMES</code>	Generate primes of <code>uint64_t</code> type.

6.1.3 Function Documentation

6.1.3.1 primesieve_count_primes()

```
uint64_t primesieve_count_primes (
    uint64_t start,
    uint64_t stop )
```

Count the primes within the interval [start, stop].

By default all CPU cores are used, use [primesieve_set_num_threads\(int threads\)](#) to change the number of threads.

Note that each call to [primesieve_count_primes\(\)](#) incurs an initialization overhead of $O(\sqrt{\text{stop}})$ even if the interval [start, stop] is tiny. Hence if you have written an algorithm that makes many calls to [primesieve_count_primes\(\)](#) it may be preferable to use a [primesieve::iterator](#) which needs to be initialized only once.

Examples

[count_primes.c](#).

6.1.3.2 [primesieve_count_quadruplets\(\)](#)

```
uint64_t primesieve_count_quadruplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime quadruplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve_set_num_threads\(int threads\)](#) to change the number of threads.

6.1.3.3 [primesieve_count_quintuplets\(\)](#)

```
uint64_t primesieve_count_quintuplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime quintuplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve_set_num_threads\(int threads\)](#) to change the number of threads.

6.1.3.4 [primesieve_count_sextuplets\(\)](#)

```
uint64_t primesieve_count_sextuplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime sextuplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve_set_num_threads\(int threads\)](#) to change the number of threads.

6.1.3.5 primesieve_count_triplets()

```
uint64_t primesieve_count_triplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime triplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve_set_num_threads\(int threads\)](#) to change the number of threads.

6.1.3.6 primesieve_count_twins()

```
uint64_t primesieve_count_twins (
    uint64_t start,
    uint64_t stop )
```

Count the twin primes within the interval [start, stop].

By default all CPU cores are used, use [primesieve_set_num_threads\(int threads\)](#) to change the number of threads.

6.1.3.7 primesieve_generate_n_primes()

```
void * primesieve_generate_n_primes (
    uint64_t n,
    uint64_t start,
    int type )
```

Get an array with the first n primes \geq start.

Parameters

<i>type</i>	The type of the primes to generate, e.g. INT_PRIMES.
-------------	--

In case an error occurs the error message is printed to the standard error stream and a NULL pointer is returned. libprimesieve also sets the C errno variable (from <errno.h>) to EDOM if any error occurs. The only advantage which checking errno (after [primesieve_generate_n_primes\(\)](#)) has over checking if a NULL pointer has been returned, is that errno is not set when calling primesieve_generate_n_primes(0, start, type) which is valid (but useless) and which returns a NULL pointer.

Examples

[primes_array.c](#).

6.1.3.8 primesieve_generate_primes()

```
void * primesieve_generate_primes (
    uint64_t start,
```

```
    uint64_t stop,
    size_t * size,
    int type )
```

Get an array with the primes inside the interval [start, stop].

Parameters

<i>size</i>	The size of the returned primes array.
<i>type</i>	The type of the primes to generate, e.g. INT_PRIMES.

In case an error occurs the error message is printed to the standard error stream, the size is set to 0 and a NULL pointer is returned. In order to distinguish an "error" from "no primes found within [start, stop]" libprimesieve also sets the C errno variable (from <errno.h>) to EDOM if any error occurs. By checking errno after calling [primesieve_generate_primes\(\)](#) users can reliably detect errors.

Examples

[primes_array.c](#).

6.1.3.9 primesieve_get_max_stop()

```
uint64_t primesieve_get_max_stop ( )
```

Returns the largest valid stop number for primesieve.

Returns

$2^{64}-1$ (UINT64_MAX).

6.1.3.10 primesieve_nth_prime()

```
uint64_t primesieve_nth_prime (
    int64_t n,
    uint64_t start )
```

Find the nth prime.

By default all CPU cores are used, use [primesieve_set_num_threads\(int threads\)](#) to change the number of threads.

Note that each call to `primesieve_nth_prime(n, start)` incurs an initialization overhead of $O(\sqrt{\text{start}})$ even if n is tiny. Hence it is not a good idea to use [primesieve_nth_prime\(\)](#) repeatedly in a loop to get the next (or previous) prime. For this use case it is better to use a [primesieve::iterator](#) which needs to be initialized only once.

Parameters

<i>n</i>	if <i>n</i> = 0 finds the 1st prime \geq start, if <i>n</i> > 0 finds the <i>n</i> th prime $>$ start, if <i>n</i> < 0 finds the <i>n</i> th prime $<$ start (backwards).
----------	---

Examples

[nth_prime.c.](#)

6.1.3.11 primesieve_set_num_threads()

```
void primesieve_set_num_threads (
    int num_threads )
```

Set the number of threads for use in `primesieve_count_*`() and [primesieve_nth_prime\(\)](#).

By default all CPU cores are used.

6.1.3.12 primesieve_set_sieve_size()

```
void primesieve_set_sieve_size (
    int sieve_size )
```

Set the sieve size in KiB (kibibyte).

The best sieving performance is achieved with a sieve size of your CPU's L1 or L2 cache size (per core).

Precondition


`sieve_size >= 16 && <= 8192.`

6.2 primesieve.hpp File Reference

primesieve C++ API.

```
#include <primesieve/iterator.hpp>
#include <primesieve/primesieve_error.hpp>
#include <primesieve/StorePrimes.hpp>
#include <stdint.h>
#include <string>
```

Include dependency graph for primesieve.hpp:



Macros

- #define PRIMESIEVE_VERSION "11.0"
- #define PRIMESIEVE_VERSION_MAJOR 11
- #define PRIMESIEVE_VERSION_MINOR 0

Functions

- template<typename vect>
void **primesieve::generate_primes** (uint64_t stop, vect *primes)
Appends the primes <= stop to the end of the primes vector.
- template<typename vect>
void **primesieve::generate_primes** (uint64_t start, uint64_t stop, vect *primes)
Appends the primes inside [start, stop] to the end of the primes vector.
- template<typename vect>
void **primesieve::generate_n_primes** (uint64_t n, vect *primes)
Appends the first n primes to the end of the primes vector.
- template<typename vect>
void **primesieve::generate_n_primes** (uint64_t n, uint64_t start, vect *primes)
Appends the first n primes >= start to the end of the primes vector.
- uint64_t **primesieve::nth_prime** (int64_t n, uint64_t start=0)
Find the nth prime.
- uint64_t **primesieve::count_primes** (uint64_t start, uint64_t stop)
Count the primes within the interval [start, stop].
- uint64_t **primesieve::count_twins** (uint64_t start, uint64_t stop)
Count the twin primes within the interval [start, stop].
- uint64_t **primesieve::count_triplets** (uint64_t start, uint64_t stop)
Count the prime triplets within the interval [start, stop].
- uint64_t **primesieve::count_quadruplets** (uint64_t start, uint64_t stop)
Count the prime quadruplets within the interval [start, stop].
- uint64_t **primesieve::count_quintuplets** (uint64_t start, uint64_t stop)
Count the prime quintuplets within the interval [start, stop].
- uint64_t **primesieve::count_sextuplets** (uint64_t start, uint64_t stop)
Count the prime sextuplets within the interval [start, stop].
- void **primesieve::print_primes** (uint64_t start, uint64_t stop)
Print the primes within the interval [start, stop] to the standard output.
- void **primesieve::print_twins** (uint64_t start, uint64_t stop)
Print the twin primes within the interval [start, stop] to the standard output.
- void **primesieve::print_triplets** (uint64_t start, uint64_t stop)
Print the prime triplets within the interval [start, stop] to the standard output.
- void **primesieve::print_quadruplets** (uint64_t start, uint64_t stop)
Print the prime quadruplets within the interval [start, stop] to the standard output.
- void **primesieve::print_quintuplets** (uint64_t start, uint64_t stop)
Print the prime quintuplets within the interval [start, stop] to the standard output.
- void **primesieve::print_sextuplets** (uint64_t start, uint64_t stop)
Print the prime sextuplets within the interval [start, stop] to the standard output.
- uint64_t **primesieve::get_max_stop** ()
Returns the largest valid stop number for primesieve.
- int **primesieve::get_sieve_size** ()
Get the current set sieve size in KiB.
- int **primesieve::get_num_threads** ()

- Get the current set number of threads.
 - void **primesieve::set_sieve_size** (int sieve_size)
Set the sieve size in KiB (kibibyte).
 - void **primesieve::set_num_threads** (int num_threads)
Set the number of threads for use in **primesieve::count_***() and **primesieve::nth_prime**().
 - std::string **primesieve::primesieve_version** ()
Get the primesieve version number, in the form "i.j".

6.2.1 Detailed Description

primesieve C++ API.

primesieve is a library for fast prime number generation, in case an error occurs a **primesieve::primesieve_error** exception (derived from **std::runtime_error**) is thrown.

Copyright (C) 2022 Kim Walisch, kim.walisch@gmail.com

This file is distributed under the BSD License.

6.2.2 Function Documentation

6.2.2.1 count_primes()

```
uint64_t primesieve::count_primes (
    uint64_t start,
    uint64_t stop )
```

Count the primes within the interval [start, stop].

By default all CPU cores are used, use **primesieve::set_num_threads(int threads)** to change the number of threads.

Note that each call to **count_primes()** incurs an initialization overhead of $O(\sqrt{\text{stop}})$ even if the interval [start, stop] is tiny. Hence if you have written an algorithm that makes many calls to **count_primes()** it may be preferable to use a **primesieve::iterator** which needs to be initialized only once.

Examples

[count_primes.cpp](#).

6.2.2.2 count_quadruplets()

```
uint64_t primesieve::count_quadruplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime quadruplets within the interval [start, stop].

By default all CPU cores are used, use **primesieve::set_num_threads(int threads)** to change the number of threads.

6.2.2.3 count_quintuplets()

```
uint64_t primesieve::count_quintuplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime quintuplets within the interval [start, stop].

By default all CPU cores are used, use `primesieve::set_num_threads(int threads)` to change the number of threads.

6.2.2.4 count_sextuplets()

```
uint64_t primesieve::count_sextuplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime sextuplets within the interval [start, stop].

By default all CPU cores are used, use `primesieve::set_num_threads(int threads)` to change the number of threads.

6.2.2.5 count_triplets()

```
uint64_t primesieve::count_triplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime triplets within the interval [start, stop].

By default all CPU cores are used, use `primesieve::set_num_threads(int threads)` to change the number of threads.

6.2.2.6 count_twins()

```
uint64_t primesieve::count_twins (
    uint64_t start,
    uint64_t stop )
```

Count the twin primes within the interval [start, stop].

By default all CPU cores are used, use `primesieve::set_num_threads(int threads)` to change the number of threads.

6.2.2.7 generate_n_primes() [1/2]

```
template<typename vect >
void primesieve::generate_n_primes (
    uint64_t n,
    uint64_t start,
    vect * primes ) [inline]
```

Appends the first n primes \geq start to the end of the primes vector.

@vect: std::vector or other vector type that is API compatible with std::vector.

6.2.2.8 generate_n_primes() [2/2]

```
template<typename vect >
void primesieve::generate_n_primes (
    uint64_t n,
    vect * primes ) [inline]
```

Appends the first n primes to the end of the primes vector.

@vect: std::vector or other vector type that is API compatible with std::vector.

Examples

[primes_vector.cpp](#).

6.2.2.9 generate_primes() [1/2]

```
template<typename vect >
void primesieve::generate_primes (
    uint64_t start,
    uint64_t stop,
    vect * primes ) [inline]
```

Appends the primes inside [start, stop] to the end of the primes vector.

@vect: std::vector or other vector type that is API compatible with std::vector.

6.2.2.10 generate_primes() [2/2]

```
template<typename vect >
void primesieve::generate_primes (
    uint64_t stop,
    vect * primes ) [inline]
```

Appends the primes \leq stop to the end of the primes vector.

@vect: std::vector or other vector type that is API compatible with std::vector.

Examples

[primes_vector.cpp](#).

6.2.2.11 get_max_stop()

```
uint64_t primesieve::get_max_stop ( )
```

Returns the largest valid stop number for primesieve.

Returns

$2^{64}-1$ (UINT64_MAX).

6.2.2.12 nth_prime()

```
uint64_t primesieve::nth_prime (
    int64_t n,
    uint64_t start = 0 )
```

Find the nth prime.

By default all CPU cores are used, use `primesieve::set_num_threads(int threads)` to change the number of threads.

Note that each call to `nth_prime(n, start)` incurs an initialization overhead of $O(\sqrt{\text{start}})$ even if n is tiny. Hence it is not a good idea to use `nth_prime()` repeatedly in a loop to get the next (or previous) prime. For this use case it is better to use a `primesieve::iterator` which needs to be initialized only once.

Parameters

<i>n</i>	if $n = 0$ finds the 1st prime $\geq \text{start}$, if $n > 0$ finds the n th prime $> \text{start}$, if $n < 0$ finds the n th prime $< \text{start}$ (backwards).
----------	---

Examples

[nth_prime.cpp](#).

6.2.2.13 set_num_threads()

```
void primesieve::set_num_threads (
    int num_threads )
```

Set the number of threads for use in `primesieve::count_*`() and `primesieve::nth_prime()`.

By default all CPU cores are used.

6.2.2.14 set_sieve_size()

```
void primesieve::set_sieve_size (
    int sieve_size )
```

Set the sieve size in KiB (kibibyte).

The best sieving performance is achieved with a sieve size of your CPU's L1 or L2 cache size (per core).

Precondition


`sieve_size >= 16 && <= 8192.`

6.3 iterator.h File Reference


[primesieve_iterator](#) allows to easily iterate over primes both forwards and backwards.

```
#include <stdint.h>
#include <stddef.h>
```

Include dependency graph for iterator.h:



This graph shows which files directly or indirectly include this file:



Classes

- struct [primesieve_iterator](#)
C prime iterator, please refer to [iterator.h](#) for more information.

Macros

- #define **IF_UNLIKELY_PRIMESIEVE**(x) if (x)

Functions

- `void primesieve_init (primesieve_iterator *it)`
Initialize the primesieve iterator before first using it.
- `void primesieve_free_iterator (primesieve_iterator *it)`
Free all memory.
- `void primesieve_clear (primesieve_iterator *it)`
Reset the start number to 0 and free most memory.
- `void primesieve_jump_to (primesieve_iterator *it, uint64_t start, uint64_t stop_hint)`
Reset the primesieve iterator to start.
- `void primesieve_skipto (primesieve_iterator *it, uint64_t start, uint64_t stop_hint)`
Reset the primesieve iterator to start.
- `static uint64_t primesieve_next_prime (primesieve_iterator *it)`
Get the next prime.
- `static uint64_t primesieve_prev_prime (primesieve_iterator *it)`
Get the previous prime.

6.3.1 Detailed Description

`primesieve_iterator` allows to easily iterate over primes both forwards and backwards.

Generating the first prime has a complexity of $O(r \log \log r)$ operations with $r = n^{0.5}$, after that any additional prime is generated in amortized $O(\log n \log \log n)$ operations. The memory usage is about $\text{PrimePi}(n^{0.5}) * 8$ bytes.

The `primesieve_iterator.c` example shows how to use `primesieve_iterator`. If any error occurs `primesieve_next_prime()` and `primesieve_prev_prime()` return `PRIMESIEVE_ERROR`. Furthermore `primesieve_iterator.is_error` is initialized to 0 and set to 1 if any error occurs.

Copyright (C) 2022 Kim Walisch, kim.walisch@gmail.com

This file is distributed under the BSD License. See the `COPYING` file in the top level directory.

6.3.2 Function Documentation

6.3.2.1 `primesieve_clear()`

```
void primesieve_clear (
    primesieve_iterator * it )
```

Reset the start number to 0 and free most memory.

Keeps some smaller data structures in memory (e.g. the PreSieve object) that are useful if the `primesieve_iterator` is reused. The remaining memory uses at most 200 kilobytes.

6.3.2.2 `primesieve_jump_to()`

```
void primesieve_jump_to (
    primesieve_iterator * it,
    uint64_t start,
    uint64_t stop_hint )
```

Reset the primesieve iterator to start.

Parameters

<code>start</code>	Generate primes \geq start (or \leq start).
<code>stop_hint</code>	Stop number optimization hint. E.g. if you want to generate the primes ≤ 1000 use <code>stop_hint = 1000</code> , if you don't know use <code>UINT64_MAX</code> .

Examples

[prev_prime.c](#), and [primesieve_iterator.c](#).

6.3.2.3 primesieve_next_prime()

```
static uint64_t primesieve_next_prime (
    primesieve_iterator * it ) [inline], [static]
```

Get the next prime.

Returns PRIMESIEVE_ERROR (UINT64_MAX) if any error occurs.

Examples

[primesieve_iterator.c](#).

6.3.2.4 primesieve_prev_prime()

```
static uint64_t primesieve_prev_prime (
    primesieve_iterator * it ) [inline], [static]
```

Get the previous prime.

`primesieve_prev_prime(n)` returns 0 for $n \leq 2$. Note that `primesieve_next_prime()` runs up to 2x faster than `primesieve_prev_prime()`. Hence if the same algorithm can be written using either `primesieve_prev_prime()` or `primesieve_next_prime()` it is preferable to use `primesieve_next_prime()`.

Examples

[prev_prime.c](#).

6.3.2.5 primesieve_skipto()

```
void primesieve_skipto (
    primesieve_iterator * it,
    uint64_t start,
    uint64_t stop_hint )
```

Reset the primesieve iterator to start.


Parameters

<code>start</code>	Generate primes > start (or < start).
<code>stop_hint</code>	Stop number optimization hint. E.g. if you want to generate the primes ≤ 1000 use <code>stop_hint = 1000</code> , if you don't know use <code>UINT64_MAX</code> .


6.4 iterator.hpp File Reference

[primesieve::iterator](#) allows to easily iterate (forwards and backwards) over prime numbers.

```
#include <stdint.h>
#include <cstddef>
#include <limits>
Include dependency graph for iterator.hpp:
```



This graph shows which files directly or indirectly include this file:



Classes

- struct [primesieve::iterator](#)

[primesieve::iterator](#) allows to easily iterate over primes both forwards and backwards.

Macros

- #define IF_UNLIKELY_PRIMESIEVE(x) if (x)

6.4.1 Detailed Description

`primesieve::iterator` allows to easily iterate (forwards and backwards) over prime numbers.


Copyright (C) 2022 Kim Walisch, kim.walisch@gmail.com

This file is distributed under the BSD License. See the COPYING file in the top level directory.


6.5 primesieve_error.hpp File Reference

The `primesieve_error` class is used for all exceptions within `primesieve`.

```
#include <stdexcept>
#include <string>
Include dependency graph for primesieve_error.hpp:
```



This graph shows which files directly or indirectly include this file:



Classes

- class [primesieve::primesieve_error](#)
primesieve throws a `primesieve_error` exception if an error occurs e.g.

6.5.1 Detailed Description

The `primesieve_error` class is used for all exceptions within `primesieve`.

Copyright (C) 2017 Kim Walisch, kim.walisch@gmail.com

This file is distributed under the BSD License. See the `COPYING` file in the top level directory.

Chapter 7

Example Documentation

7.1 count_primes.cpp

This example shows how to count primes.

This example shows how to count primes.

```
#include <primesieve.hpp>
#include <stdint.h>
#include <iostream>
int main()
{
    uint64_t count = primesieve::count_primes(0, 1000);
    std::cout << "Primes <= 1000: " << count << std::endl;
    return 0;
}
```

7.2 primesieve_iterator.cpp

Iterate over primes using [primesieve::iterator](#).

Iterate over primes using [primesieve::iterator](#).

```
#include <primesieve.hpp>
#include <cstdlib>
#include <iostream>
int main(int argc, char** argv)
{
    uint64_t limit = 10000000000ull;
    if (argc > 1)
        limit = std::atol(argv[1]);
    primesieve::iterator it(0, limit);
    uint64_t prime = it.next_prime();
    uint64_t sum = 0;
    // Iterate over the primes <= 10^9
    for (; prime <= limit; prime = it.next_prime())
        sum += prime;
    std::cout << "Sum of primes <= " << limit << ": " << sum << std::endl;
    // Note that since sum is a 64-bit variable the result
    // will be incorrect (due to integer overflow) if
    // limit > 10^10. However we do allow limits > 10^10
    // since this is useful for benchmarking.
    if (limit > 10000000000ull)
        std::cerr << "Warning: sum is likely incorrect due to 64-bit integer overflow!" << std::endl;
    return 0;
}
```

7.3 nth_prime.cpp

Find the nth prime.

Find the nth prime.

```
#include <primesieve.hpp>
#include <stdint.h>
#include <iostream>
#include <cstdlib>
int main(int, char** argv)
{
    uint64_t n = 1000;
    if (argv[1])
        n = std::atol(argv[1]);
    uint64_t nth_prime = primesieve::nth_prime(n);
    std::cout << n << "th prime = " << nth_prime << std::endl;
    return 0;
}
```

7.4 prev_prime.cpp

Iterate backwards over primes using `primesieve::iterator`.

Iterate backwards over primes using `primesieve::iterator`.

```
#include <primesieve.hpp>
#include <cstdlib>
#include <iostream>
int main(int argc, char** argv)
{
    uint64_t limit = 1000000000ull;
    if (argc > 1)
        limit = std::atol(argv[1]);
    primesieve::iterator it;
    it.jump_to(limit);
    uint64_t prime = it.prev_prime();
    uint64_t sum = 0;
    // Backwards iterate over the primes <= 10^9
    for (; prime > 0; prime = it.prev_prime())
        sum += prime;
    std::cout << "Sum of primes <= " << limit << ":" << sum << std::endl;
    // Note that since sum is a 64-bit variable the result
    // will be incorrect (due to integer overflow) if
    // limit > 10^10. However we do allow limits > 10^10
    // since this is useful for benchmarking.
    if (limit > 1000000000ull)
        std::cerr << "Warning: sum is likely incorrect due to 64-bit integer overflow!" << std::endl;
    return 0;
}
```

7.5 primes_vector.cpp

Fill a `std::vector` with primes.

Fill a `std::vector` with primes.

```
#include <primesieve.hpp>
#include <vector>
int main()
{
    std::vector<int> primes;
    // Fill the primes vector with the primes <= 1000
    primesieve::generate_primes(1000, &primes);
    primes.clear();
    // Fill the primes vector with the primes inside [1000, 2000]
    primesieve::generate_primes(1000, 2000, &primes);
    primes.clear();
    // Fill the primes vector with the first 1000 primes
    primesieve::generate_n_primes(1000, &primes);
    primes.clear();
    // Fill the primes vector with the first 10 primes >= 1000
    primesieve::generate_n_primes(10, 1000, &primes);
    return 0;
}
```

7.6 count_primes.c

C program that shows how to count primes.

C program that shows how to count primes.

```
#include <primesieve.h>
#include <inttypes.h>
#include <stdio.h>
int main()
{
    uint64_t count = primesieve_count_primes(0, 1000);
    printf("Primes <= 1000: %" PRIu64 "\n", count);
    return 0;
}
```

7.7 prev_prime.c

Iterate backwards over primes using `primesieve_iterator`.

Iterate backwards over primes using `primesieve_iterator`. Note that `primesieve_next_prime()` runs up to 2x faster and uses only half as much memory as `primesieve_prev_prime()`. Hence if it is possible to write the same algorithm using either `primesieve_prev_prime()` or `primesieve_next_prime()` then it is preferable to use `primesieve_next_prime()`.

```
#include <primesieve.h>
#include <inttypes.h>
#include <stdlib.h>
#include <stdio.h>
int main(int argc, char** argv)
{
    uint64_t limit = 10000000000ull;
    if (argc > 1)
        limit = atol(argv[1]);
    primesieve_iterator it;
    primesieve_init(&it);
    /* primesieve_jump_to(&it, start_number, stop_hint) */
    primesieve_jump_to(&it, limit, 0);
    uint64_t prime;
    uint64_t sum = 0;
    /* Backwards iterate over the primes <= limit */
    while ((prime = primesieve_prev_prime(&it)) > 0)
        sum += prime;
    primesieve_free_iterator(&it);
    printf("Sum of the primes: %" PRIu64 "\n", sum);
    /* Note that since sum is a 64-bit variable the result
     * will be incorrect (due to integer overflow) if
     * limit > 10^10. However we do allow limits > 10^10
     * since this is useful for benchmarking. */
    if (limit > 10000000000ull)
        printf("Warning: sum is likely incorrect due to 64-bit integer overflow!");
    return 0;
}
```

7.8 primesieve_iterator.c

Iterate over primes using C `primesieve_iterator`.

Iterate over primes using C `primesieve_iterator`.

```
#include <primesieve.h>
#include <inttypes.h>
#include <stdio.h>
#include <stdlib.h>
int main(int argc, char** argv)
{
    uint64_t limit = 10000000000ull;
    if (argc > 1)
        limit = atol(argv[1]);
    primesieve_iterator it;
    primesieve_init(&it);
    /* Indicate exact bounds to improve performance */
    primesieve_jump_to(&it, 0, limit);
```

```

uint64_t sum = 0;
uint64_t prime = 0;
/* Iterate over the primes <= 10^9 */
while ((prime = primesieve_next_prime(&it)) <= limit)
    sum += prime;
printf("Sum of the primes <= %" PRIu64 " : %" PRIu64 "\n", limit, sum);
primesieve_free_iterator(&it);
return 0;
}

```

7.9 nth_prime.c

C program that finds the nth prime.

C program that finds the nth prime.

```

#include <primesieve.h>
#include <stdlib.h>
#include <inttypes.h>
#include <stdio.h>
int main(int argc, char** argv)
{
    uint64_t n = 1000;
    if (argc > 1 && argv[1])
        n = atol(argv[1]);
    uint64_t prime = primesieve_nth_prime(n, 0);
    printf("%" PRIu64 "th prime = %" PRIu64 "\n", n, prime);
    return 0;
}

```

7.10 primes_array.c

Generate an array of primes.

Generate an array of primes.

```

#include <primesieve.h>
#include <stdio.h>
int main()
{
    uint64_t start = 0;
    uint64_t stop = 1000;
    size_t i;
    size_t size;
    /* Get an array with the primes <= 1000 */
    int* primes = (int*) primesieve_generate_primes(start, stop, &size, INT_PRIMES);
    for (i = 0; i < size; i++)
        printf("%i\n", primes[i]);
    primesieve_free(primes);
    uint64_t n = 1000;
    /* Get an array with the first 1000 primes */
    primes = (int*) primesieve_generate_n_primes(n, start, INT_PRIMES);
    for (i = 0; i < n; i++)
        printf("%i\n", primes[i]);
    primesieve_free(primes);
    return 0;
}

```

Index

clear
 primesieve::iterator, 11

count_primes
 primesieve.hpp, 23

count_quadruplets
 primesieve.hpp, 23

count_quintuplets
 primesieve.hpp, 23

count_sextuplets
 primesieve.hpp, 24

count_triplets
 primesieve.hpp, 24

count_twins
 primesieve.hpp, 24

generate_n_primes
 primesieve.hpp, 24

generate_primes
 primesieve.hpp, 25

get_max_stop
 primesieve.hpp, 25

INT16_PRIMES
 primesieve.h, 17

INT32_PRIMES
 primesieve.h, 17

INT64_PRIMES
 primesieve.h, 17

INT_PRIMES
 primesieve.h, 17

iterator
 primesieve::iterator, 10

iterator.h, 27

 primesieve_clear, 28

 primesieve_jump_to, 28

 primesieve_next_prime, 29

 primesieve_prev_prime, 29

 primesieve_skipto, 29

iterator.hpp, 30

jump_to
 primesieve::iterator, 11

LONG_PRIMES
 primesieve.h, 17

LONGLONG_PRIMES
 primesieve.h, 17

next_prime
 primesieve::iterator, 11

nth_prime

primesieve.hpp, 25

prev_prime
 primesieve::iterator, 11

primesieve.h, 15

 INT16_PRIMES, 17

 INT32_PRIMES, 17

 INT64_PRIMES, 17

 INT_PRIMES, 17

 LONG_PRIMES, 17

 LONGLONG_PRIMES, 17

 primesieve_count_primes, 17

 primesieve_count_quadruplets, 18

 primesieve_count_quintuplets, 18

 primesieve_count_sextuplets, 18

 primesieve_count_triplets, 18

 primesieve_count_twins, 19

 primesieve_generate_n_primes, 19

 primesieve_generate_primes, 19

 primesieve_get_max_stop, 20

 primesieve_nth_prime, 20

 primesieve_set_num_threads, 21

 primesieve_set_sieve_size, 21

 SHORT_PRIMES, 17

 UINT16_PRIMES, 17

 UINT32_PRIMES, 17

 UINT64_PRIMES, 17

 UINT_PRIMES, 17

 ULONG_PRIMES, 17

 ULONGLONG_PRIMES, 17

 USHORT_PRIMES, 17

primesieve.hpp, 21

 count_primes, 23

 count_quadruplets, 23

 count_quintuplets, 23

 count_sextuplets, 24

 count_triplets, 24

 count_twins, 24

 generate_n_primes, 24

 generate_primes, 25

 get_max_stop, 25

 nth_prime, 25

 set_num_threads, 26

 set_sieve_size, 26

primesieve::iterator, 9

 clear, 11

 iterator, 10

 jump_to, 11

 next_prime, 11

 prev_prime, 11

primesieve::primesieve_error, 12
primesieve_clear
 iterator.h, 28
primesieve_count_primes
 primesieve.h, 17
primesieve_count_quadruplets
 primesieve.h, 18
primesieve_count_quintuplets
 primesieve.h, 18
primesieve_count_sextuplets
 primesieve.h, 18
primesieve_count_triplets
 primesieve.h, 18
primesieve_count_twins
 primesieve.h, 19
primesieve_error.hpp, 31
primesieve_generate_n_primes
 primesieve.h, 19
primesieve_generate_primes
 primesieve.h, 19
primesieve_get_max_stop
 primesieve.h, 20
primesieve_iterator, 13
primesieve_jump_to
 iterator.h, 28
primesieve_next_prime
 iterator.h, 29
primesieve_nth_prime
 primesieve.h, 20
primesieve_prev_prime
 iterator.h, 29
primesieve_set_num_threads
 primesieve.h, 21
primesieve_set_sieve_size
 primesieve.h, 21
primesieve_skipto
 iterator.h, 29

set_num_threads
 primesieve.hpp, 26
set_sieve_size
 primesieve.hpp, 26
SHORT_PRIMES
 primesieve.h, 17

UINT16_PRIMES
 primesieve.h, 17
UINT32_PRIMES
 primesieve.h, 17
UINT64_PRIMES
 primesieve.h, 17
UINT_PRIMES
 primesieve.h, 17
ULONG_PRIMES
 primesieve.h, 17
ULLONG_PRIMES
 primesieve.h, 17
USHORT_PRIMES
 primesieve.h, 17